

# **IMPORTANT**

## ***Installation Instructions for EMIGMA Basic Version***

**To uninstall EMIGMA Basic, use “Control Panel” -> “Add/Remove Programs”**

Run EMIGMA\_Basic\_Setup.exe and follow the instructions of the setup program.

***Special Instructions for Windows 2000, Windows XP and Windows Vista Users:***

***--- The installer must have administrative privileges.***

***After installation it is recommended to check the following environment variables:***

1) TGS\_LICENSE\_FILE should be set to the location of the password.dat  
e.g. “c:\Program Files\Emigma\_Basic\bin\password.dat

2) Path should have the location of the “\bin” directory:  
e.g. “c:\ Program Files\Emigma\_Basic \bin

***Note: If you have installed EMIGMA BASIC into a directory other than “c:\ Program Files” ensure that you use that path in the above 2 steps.***

**Re-boot** your computer.

---

Note:

You will encounter a warning message when using EMIGMA Basic ‘TGS License File Error’. This is only a warning message. Please click OK to this message and continue normal use.

**Please contact us if you have any questions :Support Department, PetRosEiKon**

**Tel: 1 (905)-796-0324**

**Email: [support@petroseikon.com](mailto:support@petroseikon.com)**